Audacious - OLD, PLEASE USE GITHUB DISCUSSIONS/ISSUES - Bug #218

"Close Playlist" dialog ignores GTK dialog button order

November 26, 2012 06:11 - Stephan Sokolow

Status:	Closed		**Start date:**	November 26, 2012
Priority:	Minor		**Due date:**	
Assignee:			**% Done:**	0%
Category:	libaudgui		**Estimated time:**	0.00 hour
Target version:				
Affects version:	3.3.2			

Description

When gtk-alternative-button-order=0, GTK+ applications are supposed to put the OK/Yes/Confirm button to the right of the Cancel/No button. (GNOME/MacOS order)

However, contrary to every other application on my desktop (including Qt applications via GtkStyle), Audacious's "Close Playlist" dialog uses KDE/Windows button order and puts "Yes" to the left of "No".

History

#1 - November 26, 2012 16:51 - Thomas Lange

- File confirm.patch added

- Category changed from plugins/gtkui to libaudgui

Thanks for your bug report Stephan.

The bug is caused by using a GtkWindow with custom content instead of a GtkMessageDialog.
Attached is a patch which fixes this. John, please review.

Should I use a gpointer parameter in "confirm_delete_cb()"?

#2 - November 27, 2012 00:24 - John Lindgren

Looks good. Personally I prefer (void *) instead of gpointer, int instead of gint, etc.

#3 - November 27, 2012 14:32 - Thomas Lange

Fixed: https://github.com/audacious-media-player/audacious/commit/f2f1b8fc23b0e0c1ad8883c9d3b9789837807438

#4 - November 27, 2012 14:32 - Thomas Lange

- Status changed from New to Resolved

#5 - November 27, 2012 14:32 - Thomas Lange

- Status changed from Resolved to Closed

Files

snapshot1.png	19.8 KB	November 26, 2012	Stephan Sokolow
snapshot2.png	10.8 KB	November 26, 2012	Stephan Sokolow
snapshot3.png	18.8 KB	November 26, 2012	Stephan Sokolow
confirm.patch	4.42 KB	November 26, 2012	Thomas Lange